



Quick Move Database to Another PC

Overview

There are four main steps in moving the Elite System from one PC to another;

1. Backup your data from the old PC
2. Install the software on the new PC
3. Copy the backed up data into the new PC
4. Configure the XL Unloader program and check everything.

Backup your data from the old PC

There are two directories to save ;

1. C:\EliteData. This and all included
2. C:\Program File\Elite ID\EliteReporter\db. The "db" directory is your database.

Performing the actual backup depends on your PC. You may be able to use a CD Burner, or a USB Memory stick or copy the data to a networked PC.

Install the software on the new PC

Use your Elite Voyager CD to install all the Elite software.

Allow it to install by all the standard options.

Copy the backed up data into the new PC

Put the backed up data into the new PC in the same places as they were taken out of the old PC. Note that you will be asked if you want to "overwrite" (say yes to all) directories which are already in the new PC.

Configure the XL Unloader program